

Table of Contents

Introduction to Smart Golf Scorecard.....	2
System Requirements.....	2
Features.....	2
Integration with GolfScorecard.ws.....	2
Golfers.....	2
Clubs.....	2
Screenshots.....	3
Main Screen.....	3
Settings.....	4
Rounds.....	5
Scorecard.....	6
Active Round.....	7
Known Issues.....	7
1. Nothing happens when pressing on the Smart Golf Scorecard icon.....	7
2. Error occurs the first time the application runs.....	7
3. Uploaded scorecard does not exist in the website.....	8

Smart Golf Scorecard 1.0 User Guide

Introduction to Smart Golf Scorecard

Smart Golf Scorecard was created to minimize the amount of data entry a golfer has to do. Using this application on the course allows the golfer to quickly see the round score totals, stats and other data. After the round the golfer has the ability to synchronize their scorecard recorded in Smart Golf Scorecard with GolfScorecard.ws website.

System Requirements

In order to run Smart Golf Scorecard the following are required:

1. PocketPC or Windows Mobile 5 and above device
2. NETCFv35 (.Net Compact Framework 3.5)
3. SQL Server CE 3.5 SP1

Features

Here's a list of what the Smart Golf Scorecard has to offer.

Integration with GolfScorecard.ws

Golfers

Smart Golf Scorecard stores a list of golfers for whom you can enter and submit scorecard. During synchronization with GolfScorecard.ws this list is deleted from the application and then updated with golfers you have added to your groups in GolfScorecard.ws. In order to submit a scorecard for yourself you need to be a member of at least one of your groups. All members need to be approved. The members that are not approved will not be downloaded to the local database and therefore you will not be able to submit scorecards for them.

Clubs

During synchronization, the Smart Golf Scorecard updates the local database with a list of your favorite clubs in GolfScorecard.ws. This includes club name and course (tee) details. To get a new club/course into the application you should first make sure it is entered in the website. Then make sure to add it to your favorites list. Lastly, synchronize with the website.

Smart Golf Scorecard 1.0 User Guide

Screenshots

This section will be updated with details but for now at least we have the screenshots.


Main Screen


On this screen you can download golfer and club data from GolfScorecard.ws. Once you have completed a round you can also upload your rounds to GolfScorecard.ws by clicking on **Upload Rounds**. As you can see from the screenshot, Active Round Summary provides a list of golfers and courses (tees) they are playing as well as what their scores are. The first time you use this application, you should setup the username and password. This login information should be the same as the login you use in GolfScorecard.ws. To enter your login, click on **Menu** then **Settings**.



Before you can create any rounds you will need to **Download Golfers** and **Download Clubs**. Make sure you have configured the settings before clicking these buttons.

In order to get any golfers transferred from GolfScorecard.ws you will need to make sure you have created a group in the website. You will have to add yourself to the group and any other person that you will be keeping score for. Once you have the group setup on the website then you can click **Download Golfers** to transfer the golfers' data over to this application.

In order to get any clubs data transferred from GolfScorecard.ws you will need to add clubs to your favorites. To do so, search for your favorite club. Once found go to the club's profile page. There click on the yellow star icon []. Once you have set at least one favorite club, you can click the Download Clubs button to transfer the clubs' data from GolfScorecard.ws to this application.



Smart Golf Scorecard 1.0 User Guide

Settings

The username and password is used to authenticate the transmissions between this application and GolfScorecard.ws. It is also used to identify your groups and favorite clubs.



Smart Golf Scorecard 1.0 User Guide

Rounds

In order to enter your scorecard information you will need to setup a round. To get to this screen in the main screen click **Menu** then **Rounds**. Here you can create a new round, edit, delete or activate existing rounds. In order to enter scores and stats you will need to have a round activated. To do so, select a round and click **Activate**. That round record will be highlighted with a green color. If you would like to activate a different round then simply select that round and click **Activate**.



When deleting a round be warned this will delete all scorecard data associated with the round. So if you have completed a round but have not Uploaded it to GolfScorecard.ws then you will lose this round's information. It is recommended to first upload the round to GolfScorecard.ws and then to delete it from this application.

Smart Golf Scorecard 1.0 User Guide

Scorecard

To get to this screen, from the Rounds screen's Round menu item click on new. When creating a new round you will need to select a Club, Date, Type (All, Front, Back), and Golfers with the tees they will be playing. To add golfers to this round click on the plus icon [+]. This will open **Add Golfer to Scorecard** screen. There you will be able to select a golfer and the course (tee) that he or she will be playing.

In the event that you make a mistake and would need to remove a golfer select a row and click on the minus icon [-].

Make sure to click Save to apply your changes.



Smart Golf Scorecard 1.0 User Guide

Active Round

This is where you will be for most of the time. Once you have created a round and have activated it you will be able to go to this screen. To get to this screen, from the main screen, click on the **Active Round** menu item. Make sure to have activated a round before clicking the menu item.



When the screen first loads it will start with the first hole. Depending on the round type this could be hole one or hole ten. After setting a score and various stats make sure to click **Save and Stay** or **Save and Next**.

Clicking **Save and Stay** allows you to save the selected hole and golfer's information and remain on the same record.

Clicking **Save and Next** will advance to the next golfer (if another one exists). If already at the last golfer or there is only one golfer in the drop down, then it will advance to the next hole.

Known Issues

This is a list of issues you may run into while using this application. With each issue there is a workaround provided.

1. Nothing happens when pressing on the Smart Golf Scorecard icon.

This issue occurs when .NET Compact Framework 3.5 has not been installed on the device. .NET Compact Framework 3.5 must be installed before running the application.

2. Error occurs the first time the application runs

This issue occurs when SQL Server CE 3.5 SP1 has not been installed on the device. SQL Server CE 3.5 SP1 must be installed before running the application.

3. Uploaded scorecard does not exist in the website

This issue will occur for those located outside United States where the date is NOT in the **mm/dd/yyyy** format. Workaround is to change your device's setting to display the date in the **mm/dd/yyyy** format.